


Inhaltsverzeichnis

Timer Editor	3
<i>Explanation of the keys</i>	3
<i>Editor Explanation</i>	4
<i>Show Name</i>	4
<i>Channel Selection</i>	4
<i>Date setting</i>	5
<i>Recording mode</i>	6
Record	6
Blocked	6
Zap & record	6
Zap	6
Remind	7
<i>Setting the start & End time</i>	7
<i>Adjustment of Prepad & Postpad</i>	7
<i>After event setting</i>	8
<i>Repeat settings</i>	9
<i>Record path setting</i>	10
<i>Setting the search</i>	12
<i>Delete settings</i>	13
<i>File Name</i>	14

Timer Editor

These settings are structured identically in the [Guide View](#), [Overview view](#), [Grid view](#) and [Next event view](#).



Explanation of the keys



- Save created timer
- On/Off. The start and end time of a recording is adjusted to the EPG data. In the Vti Timer Menu setting, "Automatically adapt recording time to EPG data" must be activated
- On/Off. For the VPS on option, the VPS plugin must be activated
- Edit highlighted timer
- Exit

Depending on the input field, the following keys appear in the editor



- Switch back one station with the left control pad button
- Use the right control pad button to switch to a station
- Depending on the input option, switch back 10 channels or 15 minutes
- Depending on the input option, switch 10 stations forward or 15 minutes back
- Depending on the input option, switch back 10 channels or 1 minute
- Depending on the input option, switch back 10 stations or forward 1 minute
- Edit entry or change mode in the next field, i.e. Power off, Automatic, Standby or none
- Take over the name of the program from the first input field in the recording path, then the recording will be saved in this path

Editor Explanation

The following screenshots show the various keys of the respective fields, depending on where you are.




The blue framed text shows which setting is explained below the screenshot.



The VPS and EPG function is explained [HERE](#) in detail.

Show Name



The framed field shows the title of the program to be recorded. This can be edited with .

Channel Selection

Timer list

 HD	Sat 16.04	9-1-1 Notruf L.A. - S02E09 – Wahre Bestimmung	5/27
 HD	Sat 16.04	9-1-1 Notruf L.A. - S02E10 – Weihnachtswunder	20:09 – 21:47 4/97'
 HD	Sun 17.04	SmartEPGvu	21:12 – 22:48 96'
 31	Sun 17.04	Image-Sicherung	06:00 – 06:01
 HD	Tue 19.04	Two and a Half Men	08:05 – 08:06
 31	Tue 19.04	VPS - Plugin	07:07 – 07:43 36'
 HD	Tue 19.04	In aller Freizeit	12:35 – 12:36
 HD	Tue 19.04	Two and a Half Men	12:45 – 13:45 60'
 HD	Tue 19.04	Two and a Half Men	13:40 – 14:18 38'
 2DF	Tue 19.04	SOKO Köln - S05E10	14:08 – 14:46 38'
 1 HD	Tue 19.04	WaPo Berlin	17:55 – 19:05 70'
 HD	Wed 20.04	Morden im	18:45 – 19:50 65'
 HD	Wed 20.04	Two and a Half Men - S06E10 – Der Schwachkopf kriegt ein Auto	12:45 – 13:50 65'
 HD	Wed 20.04	Two and a Half Men - S06E10 – Der Schwachkopf kriegt ein Auto	13:41 – 14:19 37'

Save Timer Auto EPG adjust on VPS mode

  +/- Channel   +/- 10 Channels  Switch bouquet

 Exit

SmartEPGvu⁺

The framed field indicates the station for the recording. With the keys     the channel selection be changed.

Date setting

Timer list

 2DF HD	Thu 03.02	SOKO Stuttgart - Krankes System	1/18
 HD	Thu 03.02	RTL Aktuell	17:55 – 19:30 95'
 HD	Thu 03.02	RTL Aktuell	18:45 – 19:18 33'
 31	Thu 03.02	VPS - Plugin	18:58 – 19:34 36'
 1 HD	Thu 03.02	Wetter vorab	19:35 – 19:36
 2DF	Thu 03.02	Der Bergdoktor	19:45 – 20:25 40'
 HD	Fri 04.02	SmartEPGvu	20:10 – 22:15 125'
 HD	Fri 04.02	RTL Aktuell	06:00 – 06:01
 HD	Fri 04.02	RTL Aktuell	18:45 – 19:18 33'
 2DF	Fri 04.02	Der Staatsanwalt	18:58 – 19:35 37'
 HD	Sat 05.02	RTL Aktuell	20:10 – 21:45 95'
 HD	Sun 06.02	Image-Sicherung	18:45 – 19:18 33'
 31	Sun 06.02	RTL Aktuell	08:05 – 08:06
 HD	Sun 06.02	RTL Aktuell	18:45 – 19:18 33'

Save Timer Auto EPG adjust on VPS mode

 Edit date  Exit

SmartEPGvu⁺

The framed box indicates the scheduled date of recording. The date can be edited with the .

Recording mode



With  or   the mode of recording can be changed. The following options are available:

Record

The program is recorded

Blocked

The program will not be recorded

Zap & record

Switches to the recording station and the program is recorded

Zap

It is only switched to the recording station without recording

Remind

A so-called M-Timer is created and a reminder is displayed at the set start of the show

Setting the start & End time



The framed box indicates the scheduled start time of the recording.

The time can be edited with the  keys. This also applies to the **end times**.

Adjustment of Prepad & Postpad

Timer list

1/18

 Thu 03.02	SOKO Stuttgart - Krankes System	17:55 – 19:30	 95'
 Thu 03.02	RTL Aktuell	18:45 – 19:18	 33'
 Thu 03.02	RTL Aktuell	18:58 – 19:34	 36'
 Thu 03.02	VPS – Plugin	19:35 – 19:36	
 Thu 03.02	Wetter vorab	19:45 – 20:25	 40'
 Thu 03.02	Der Bergdoktor	20:10 – 22:15	 125'
 Fri 04.02	SmartEPGv	06:00 – 06:01	
 Fri 04.02	RTL Aktuell	18:45 – 19:18	 33'
 Fri 04.02	RTL Aktuell	18:58 – 19:35	 37'
 Fri 04.02	Der Staatsanwalt	20:10 – 21:45	 95'
 Sat 05.02	RTL Aktuell	18:45 – 19:18	 33'
 Sun 06.02	Image-Sicherung	08:05 – 08:06	
 Sun 06.02	RTL Aktuell	18:45 – 19:18	 33'

SOKO Stuttgart

2. ZDF HD

Date: Thu 03.02.2022 Mode: Record

Start time: 18:00 End time: 19:00 (60 min)

Prepad: 5 min Postpad: 30 min

After event: Auto Repeat: off

Record path: /media/hdd/movie/

Search: SOKO

Delete after 0 hours Delete on low space: No

File name: VTi settings

Save Timer Auto EPG adjust on VPS mode

  +/- 1 min   +/- 15 min 

 Exit

SmartEPGv⁺

The framed field shows the Prepad for the recording.

With the keys     you can advance be adjusted. This also applies to the **Postpad**.

With the key  neither a Prepad nor a Postpad is set.

After event setting

The screenshot shows the SmartEPGv+ software interface. On the left, a list of scheduled timers is displayed. On the right, a detailed configuration dialog is open for a specific timer. The timer details are as follows:

- Station:** SOKO Stuttgart
- Program:** 2. ZDF HD
- Date:** Thu 03.02.2022
- Mode:** Record
- Start time:** 18:00
- End time:** 19:00 (60 min)
- Prepad:** 5 min
- Postpad:** 30 min
- After event:** Auto
- Repeat:** off
- Record path:** /media/hdd/movie/
- Search:** SOKO
- Delete after 0 hours:** No
- Delete on low space:** No
- File name:** VTi settings

At the bottom of the interface, there are several control buttons and a logo:

- Save Timer
- Auto EPG adjust on
- VPS mode
- Change mode
- Exit

SmartEPGv+⁺

With you can set what the Vu+ should do after the recording. The following options are available:

Auto > None > Standby > Deep Standby

Repeat settings

Timer list

1/18

	Thu 03.02	SOKO Stuttgart - Krankes System	17:55 – 19:30	95'
	Thu 03.02	RTL Aktuell	18:45 – 19:18	33'
	Thu 03.02	RTL Aktuell	18:58 – 19:34	36'
	Thu 03.02	VPS - Plugin	19:35 – 19:36	1'
	Thu 03.02	Wetter vorab	19:45 – 20:25	40'
	Thu 03.02	Der Bergdoktor	20:10 – 22:15	125'
	Fri 04.02	SmartEPGv	06:00 – 06:01	1'
	Fri 04.02	RTL Aktuell	18:45 – 19:18	33'
	Fri 04.02	RTL Aktuell	18:58 – 19:35	37'
	Fri 04.02	Der Staatsanwalt	20:10 – 21:45	95'
	Sat 05.02	RTL Aktuell	18:45 – 19:18	33'
	Sun 06.02	Image-Sicherung	08:05 – 08:06	1'
	Sun 06.02	RTL Aktuell	18:45 – 19:18	33'

Save Timer Auto EPG adjust on VPS mode
 Edit repeat Exit

SmartEPGv⁺

Repetitions can be defined with the following keys after pressing the key:

Save repeat Off Mon Tue Wed Thu Fri Sat Sun Work days weekend

Record path setting

Timer list


2/21

	Mon 21.02	VPS - Plugin	18:35 – 18:36	1'
	Mon 21.02	RTL Aktuell	18:45 – 19:08	23'
	Mon 21.02	Morden im	18:45 – 19:55	70'
	Mon 21.02	Gute Zeiten	19:30 – 20:30	60'
	Mon 21.02	All Rise - Die	20:09 – 21:38	89'
	Mon 21.02	All Rise - Die	21:03 – 22:33	89'
	Tue 22.02	SmartEPGv	06:00 – 06:01	1'
	Tue 22.02	Navy CIS - S	20:09 – 21:19	69'
	Wed 23.02	RTL Aktuell	18:45 – 19:08	23'
	Wed 23.02	Gute Zeiten	19:30 – 20:30	60'
	Thu 24.02	RTL Aktuell	18:45 – 19:08	23'
	Thu 24.02	Gute Zeiten	19:30 – 20:30	60'
	Fri 25.02	RTL Aktuell	18:45 – 19:08	23'

Save Timer Bookmarks Auto EPG adjust on VPS mode
 Select path Add name to path
 Exit

SmartEPGv⁺

With the  (PVR button) the name of the program can be taken over from the first field.



Alternatively, the folder for saving the recording can be selected with .

Bookmarks can also be selected with the  key. These are identical to the bookmarks managed by the VTi.

The image shows the SmartEPGv+ user interface. On the left, a 'Timer list' displays a grid of scheduled events. On the right, a 'Select favorite folder' menu is open, listing various media paths. At the bottom, a series of navigation buttons are visible.

Timer list (Left):

- 31 Mon 21.02 VPS - Plugin
- RTL HD Mon 21.02 RTL Aktuell
- 1 HD Mon 21.02 Morden im
- RTL HD Mon 21.02 Gute Zeiten
- 1 HD Mon 21.02 All Rise - Die
- 1 HD Mon 21.02 All Rise - Die
- SmartEPGv+ Tue 22.02 SmartEPGv+
- RTL HD Tue 22.02 Navy CIS - S
- RTL HD Wed 23.02 RTL Aktuell
- RTL HD Wed 23.02 Gute Zeiten
- RTL HD Thu 24.02 RTL Aktuell
- RTL HD Thu 24.02 Gute Zeiten
- RTL HD Fri 25.02 RTL Aktuell

Select favorite folder (Right):

- RTI Aktuell
- Select favorite folder
- 4 /media/hdd/
- S /media/hdd/ ...
- P /media/hdd/movie/ ...
- A /media/hdd/movie/Alle Krimis/
- R /media/net/autonet/DISKSTATION_TEN/ ...
- S /media/net/autonet/DISKSTATION_TEN/Soko/
- D
- C
- F

Bottom Buttons:


- Select folder (Green circle)
- Show folder (Blue circle)
- Enter folder (Green circle)
- Delete bookmark (Blue circle)
- Exit (Blue circle)

SmartEPGv+ logo:

It is also possible to select the directory marked with the cursor by pressing the key or you can select a directory from the movie list.

Setting the search


With the key you can switch to **Search view**. Unless a search request has been created for the timer, this field cannot be edited.



Delete settings

Delete after hours: The recording will be deleted after a specified time.
This routine is called up once an hour and deletes the recordings after the set expiry time.


Delete when there is insufficient space: The recording is automatically deleted when there is no more space on the hard drive (currently hard coded to 15GB)



File Name

Use the left and right keys to select which suffix should be added to the recording name. The options are:

- vu+ standard
- Name
- Name + Description
- Name + Timestamp
- Name + Description or Time
- Name + Description + Time
- Name + Time + Description



If you have not selected „vu+ default values“ in a search or in the global settings, the recording will be renamed after the end of the recording. If a recording with the same name already exists, the newer one is given the suffix „-2“, „-3“, etc.

From:

<https://www.nayal.de/> -

Permanent link:

<https://www.nayal.de/doku.php/en:timereditor>

Last update: **2024/01/14 19:39**



